
eBeam Marker Developer Guide for Android

Luidia R&D S/W

2017. 11

- Copy eBeamMarkerSDK-v1.0-20180504-release.aar to libs/
- Add Permission and service in the [AndroidManifest.xml](#)
 - <uses-permission android:name="android.permission.WAKE_LOCK" />
 - <uses-permission android:name="android.permission.BLUETOOTH" />
 - <uses-permission android:name="android.permission.BLUETOOTH_ADMIN" />
 - <service
 android:name="com.luidia.ebeam.sdk.UartService"
 android:enabled="true" />

Development > Components of Test Sample (PenTest)

Folder		File	Description
\$(SDKHome)/src/com/pnf/pen	calibration/	CalibrationMarkerActivity.java	Calibration Activity
	device/	PNFBluetoothViewActivity.java	Device Connect Activity
		DeviceChangeNameViewActivity.java	Device Name Change Activity
		DeviceChangeAudioViewActivity.java	Device Audio Change Activity
	drawingview/	DrawView.java	Drawing View Class
		DrawViewActivity.java	Drawview Activity
	test/	BaseActivity.java	Base Activity
		MainActivity.java	Main Activity
		MainDefine.java	Define Class
\$(SDKHome)/res/layout		activity_main.xml	Main layout
		baseview.xml	Base layout
		activity_calibration_marker.xml	Layout for calibration
		bluetooth_connect_view.xml	Layout for connect
		activity_device_change_name_view.xml	Layout for change name
		activity_device_change_audio_view.xml	Layout for change audio
		drawview.xml	Layout for drawing

➤ Methods

new		
Description	Create object of EBeamPenController	
out	N/A	
input	Context	Context of application
Device	eBeam Marker	
Usage	<pre>@Override public void onCreate(Bundle savedInstanceState) { MainDefine.penController = EBeamPenController.create(getApplicationContext()); MainDefine.penController.setModelCode(ModelCode.eBeamSmartMaker); }</pre>	

getModelCode		
Description	Get Connected device	
Out	int	
input	N/A	
Device	eBeam Marker	
Usage	<pre> public void onActivityResult(int requestCode, int resultCode, Intent data) { if(requestCode == REQUEST_BLUETOOTH_CONNECT) { modelCodeValueTextView.setText(String.valueOf(MainDefine.penController.getModelCode())); hwVerValueTextView.setText("" + MainDefine.penController.getHWVersion()); nameValueTextView.setText("" + MainDefine.penController.getStationName()); } } </pre>	

setPenEventListener		
Description	Set an object to receive the pen data	
Out	Void	
input	PenEventListener	Object pointer to receive the pen data
Device	eBeam Marker	
Usage	<pre>protected void onResume() { super.onResume(); MainDefine.penController.setPenEventListener(new PenEventListener() { @Override public void onPenEvent(int what, int arg1, int arg2, Object obj) { } }) }</pre>	

setRetObjForMsg		
Description	Set an object to receive the pen data for Message	
Out	Void	
input	PenMessageListener	
Device	eBeam Marker	
Usage	<pre>protected void onResume() { super.onResume(); MainDefine.penController.setPenMessageListener(new PenMessageListener() { @Override public void onPenMessage(int what, int arg1, int arg2, Object obj) { } }) }</pre>	

setCalibrationSendStart		
Description	Set data for calibration	
Out	Void	
input	N/A	
Device	eBeam Marker	
Usage	<pre>void setCalibrationSendStart(){ MainDefine.penController.startCalibMode(); }</pre>	

setCalibrationSendStop		
Description	Set data for calibration	
Out	Void	
input	N/A	
Device	eBeam Marker	
Usage	<pre>void setCalibrationSendStop(){ MainDefine.penController.stopCalibMode(); }</pre>	

setCalibrationSendData		
Description	Set data for calibration	
Out	Void	
input	DeviceDirection	DEVICE_DIRECTION_LEFT
	PointF	Calibration Raw data
Device	eBeam Marker	
Usage	<pre>void coordinateComplete (){ MainDefine.penController.setCalibrationSendData(setCaliPosition, m_posRestultPoint[0], m_posRestultPoint[3], m_posRestultPoint[2], m_posRestultPoint[1]); }</pre>	

setChangeNameSend		
Description	Set data for Name Change	
Out	Void	
input	changeDeviceName	Device name
Device	eBeam Marker	
Usage	<pre>void setChangeNameSend (){ MainDefine.penController. setDeviceNameData(changeDeviceName); }</pre>	

setDeviceAudioData		
Description	Set data for calibration	
Out	Void	
input	DeviceAudio	DEVICE_AUDIO_LANG_ENGLISH
Device	eBeam Marker	
Usage	MainDefine.penController.setDeviceAudioData(audioCode);	

getCoordinatePosition		
Description	Get calibrated coordinates	
Out	PointF	
input	N/A	
Device	eBeam Marker	
Usage	<pre>void onPenEvent(int what, int RawX, int RawY ,Object obj) { PointF ptConv = MainDefine.penController. getCoordinatePosition(RawX,RawY,penData.bRight); }</pre>	

➤ Overview

Create and initialize object `EBeamPenController`

➤ Example

1. Create `EBeamPenController` object
`MainDefine.penController = EBeamPenController.create(getApplicationContext());`
2. Set Default Device Model
`MainDefine.penController.setDefaultModelCode(PNFDefine.eBeamSmartMaker);`

➤ Overview

Internally EBeamPenController is supposed to call selector named as "PenEventListener" of object set by "setPenEventListener" whenever the pen moves.

➤ Example

```
void onPenEvent(int what, int RawX, int RawY ,Object obj)
{
    PenData penData = (PenData)obj;
    PointF ptConv = MainDefine.penController.GetCoordinatePostionXY(RawX ,RawY ,penData.bRight);

    switch(what)
    {
        case PenEvent.PEN_DOWN:
            switch(penData.MakerPenStatus){
                case PenEvent.MARKERPEN_RED_MARKER:
                    break;
                case PenEvent.MARKERPEN_GREEN_MARKER:
                    break;
                case PenEvent.MARKERPEN_YELLOW_MARKER:
                    break;
                case PenEvent.MARKERPEN_BLUE_MARKER:
                    break;
                case PenEvent.MARKERPEN_PURPLE_MARKER:
                    break;
                case PenEvent.MARKERPEN_BLACK_MARKER:
                    break;
                case PenEvent.MARKERPEN_ERASER_CAP:
                    break;
                case PenEvent.MARKERPEN_BIG_ERASER:
                    break;
            }
            break;
        case PenEvent.PEN_MOVE:
            break;
        case PenEvent.PEN_UP:
            break;
    }
    .....
}
```

example source : MainActivity.java

➤ Overview

➤ Example

1. Set messageListener

```
protected Handler messageHandler = new Handler(){
MainDefine.penController.setPenMessageListener(this);

    @Override
    public void handleMessage(Message msg) {
        onMessageEvent(msg.what ,msg.arg1 ,msg.arg2 ,msg.obj);
    }
};
```

1. Handler for Message

```
private PenMessageListener listener = new PenMessageListener() {

    @Override
    public void onPenMessage(int what, int i1, int i2, Object o) {
        .....
        if(what == PenMessage.PNF_MSG_FAIL_LISTENING){
        }else if(what == PenMessage.PNF_MSG_CONNECTED){
        }
        else if(what == PenMessage.PNF_MSG_INVALID_PROTOCOL){
        }
        else if(what == PenMessage.PNF_MSG_SESSION_CLOSED){
        }
        else if(what == PenMessage.PNF_MSG_PEN_RMD_ERROR){
        }
        else if(what == PenMessage.PNF_MSG_FIRST_DATA_RECV){
        }
        packetCnt++;
        updatePacketCnt();
        .....
    }
}
```

Log String Message	Description
PNF_MSG_CONNECTED	Device is connected
PNF_MSG_FAIL_LISTENING	Fail to receive. Need to reconnect.
PNF_MSG_INVALID_PROTOCOL	Invalid hardware
PNF_MSG_SESSION_CLOSED	Session is disconnected
PNF_MSG_FIRST_DATA_RECV	First data is received after connecting
PNF_MSG_PEN_RMD_ERROR	Abnormal drawing data

➤ Overview

Pen coordinates is converted to screen coordinates by projective matrix which is set in the calibration view.

➤ Example

1. Override interface for pen data and message event

```
@Override
void onPenEvent(int what, int RawX, int RawY ,Object obj) {
    ..... }

@Override
void onMessageEvent(int what, int RawX, int RawY ,Object obj) {
    ..... }
```

2. set handler for pen data

```
MainDefine.penController.setPenEventListener(this);
MainDefine.penController.setPenMessageListener(this);
```